Lecture 4: Function invocations, and calling conventions

Anton Burtsev
October, 2021

Recap: stack

Stack

- It's just a region of memory
  - Pointed by a special register ESP
- You can change ESP
  - Get a new stack



Stack allows us to invoke functions

Calling functions

```
// some code...
foo();
// more code..
```

- Stack contains information for how to return from a subroutine
  - i.e., from foo()

- Functions can be called from different places in the program

```
if (a == 0) {
     foo();
     …
} else {
     foo();
     …
}
```

Stack

- Main purpose:
  - Store the return address for the current procedure
  - Caller pushes return address on the stack
  - Callee pops it and jumps



Stack

- Main purpose:
  - Store the return address for the current procedure
  - Caller pushes return address on the stack
  - Callee pops it and jumps



Example

```
foo(int a) {
    if (a == 0)
        return;
    a--;
    foo(a);
    return;
}

foo(4);
```

Calling conventions

Calling conventions

- Goal: re-entrant programs
  - How to pass arguments
    - On the stack?
    - In registers?
  - How to return values
    - On the stack?
    - In registers?
- Conventions differ from compiler, optimizations, etc.

Maintain stack as frames

- Each function has a new frame

```
void DrawSquare(...)
{
    ...
    DrawLine(x, y, z);
}
```

- Use dedicated register **EBP** (frame pointer)
  - Points to the base of the frame



Maintain stack as frames

- Each function has a new frame

```
void DrawSquare(...)
{
    ...
    DrawLine(x, y, z);
}
```

- Use dedicated register **EBP** (frame pointer)
  - Points to the base of the frame



Stack consists of frames

- Each function has a new frame

```
void DrawSquare(...)
{
    ...
    DrawLine(x, y, z);
}
```

- Use dedicated register **EBP** (frame pointer)
    - Points to the base of the frame



Prologue/epilogue

- Each function maintains the frame
  - A dedicated register EBP is used to keep the frame pointer
  - Each function uses prologue code (blue), and epilogue (yellow) to maintain the frame

```
my_function:
    push ebp            ; save original EBP value on stack
    mov ebp, esp        ; new EBP = ESP
    ….                  ; function body
    pop ebp             ; restore original EBP value
    ret
```

Local variables

What types of variables do you know?

- Or where these variables are allocated in memory?

What types of variables do you know?

- Global variables
  - Initialized → data section
  - Uninitalized → BSS
- Dynamic variables
  - Heap
- Local variables
  - Stack

Global variables

```
#include <stdio.h>

char hello[] = "Hello";
int main(int ac, char **av)
{
	static char world[] = "world!";
	printf("%s %s\n", hello, world);
	return 0;
}
```

Global variables

```c
#include <stdio.h>

char hello[] = "Hello";
int main(int ac, char **av)
{
    static char world[] = "world!";
    printf("%s %s\n", hello, world);
    return 0;
}
```

- Allocated in the data section
  - It is split in initialized (non-zero), and non-initialized (zero)
  - As well as read/write, and read only data section

Global variables

Dynamic variables (heap)

```c
#include <stdio.h>
#include <string.h>
#include <stdlib.h>

char hello[] = "Hello";
int main(int ac, char **av)
{
    char world[] = "world!";
    char *str = malloc(64);
    memcpy(str, "beautiful", 64);
    printf("%s %s %s\n", hello, str, world);
    return 0;
}
```

Dynamic variables (heap)

```c
#include <stdio.h>
#include <string.h>
#include <stdlib.h>

char hello[] = "Hello";
int main(int ac, char **av)
{
    char world[] = "world!";
    char *str = malloc(64);
    memcpy(str, "beautiful", 64);
    printf("%s %s %s\n", hello, str, world);
    return 0;
}
```

- Allocated on the heap
  - Special area of memory provided by the OS from where malloc() can allocate memory

Dynamic variables (heap)

Local variables

- Local variables

```
#include <stdio.h>

char hello[] = "Hello";
int main(int ac, char **av)
{
    //static char world[] = "world!";
    char world[] = "world!";
    printf("%s %s\n", hello, world);
    return 0;
}
```

Local variables...

- Each function has private instances of local variables

```
foo(int x) {
    int a, b, c;
    ...
    return;
}
```

- Function can be called recursively

```
foo(int x) {
    int a, b, c;
    a = x + 1;
    if ( a < 100 )
        foo(a);
    return;
}
```

How to allocate local variables?

```
void my_function()
{
    int a, b, c;
    …
}
```

How to allocate local variables?

```
void my_function()
{
    int a, b, c;
    …
}
```

- On the stack!

Allocating local variables

- Stored right after the saved EBP value on the stack
- Allocated by subtracting the number of bytes required from ESP

```
_my_function:
    push ebp                    ; save original EBP value on stack
    mov ebp, esp                ; new EBP = ESP
    sub esp, LOCAL_BYTES        ; = # bytes needed by locals
    …                           ; function body
    mov esp, ebp                ; deallocate locals
    pop ebp                     ; restore original EBP value
    ret
```

Example

```
void my_function() {
    int a, b, c;
    …
```

```
_my_function:
   push ebp      ; save the value of ebp
   mov ebp, esp ; ebp = esp, set ebp to be top of the stack (esp)
   sub esp, 12  ; move esp down to allocate space for the
                ; local variables on the stack
```

- With frames local variables can be accessed by dereferencing EBP

```
mov [ebp -  4], 10  ; location of variable a
mov [ebp -  8], 5   ; location of b
mov [ebp - 12], 2   ; location of c
```

Example

```
void my_function() {
    int a, b, c;
    …

_my_function:
   push ebp      ; save the value of ebp
   mov ebp, esp  ; ebp = esp, set ebp to be top of the stack (esp)
   sub esp, 12   ; move esp down to allocate space for the
                 ; local variables on the stack
```

- With frames local variables can be accessed by dereferencing EBP

```
mov [ebp -  4], 10   ; location of variable a
mov [ebp -  8], 5    ; location of b
mov [ebp - 12], 2    ; location of c
```

Example

```
void my_function() {
    int a, b, c;
    …

_my_function:
   push ebp      ; save the value of ebp
   mov ebp, esp  ; ebp = esp, set ebp to be top of the stack (esp)
   sub esp, 12   ; move esp down to allocate space for the
                 ; local variables on the stack
```

- With frames local variables can be accessed by dereferencing EBP

```
mov [ebp -  4], 10  ; location of variable a
mov [ebp -  8], 5   ; location of b
mov [ebp - 12], 2   ; location of c
```

Example

```
void my_function() {
    int a, b, c;
    …
```

```
_my_function:
   push ebp      ; save the value of ebp
   mov ebp, esp  ; ebp = esp, set ebp to be top of the stack (esp)
   sub esp, 12   ; move esp down to allocate space for the
                 ; local variables on the stack
```

- With frames local variables can be accessed by dereferencing EBP

```
mov [ebp -  4], 10  ; location of variable a
mov [ebp -  8], 5   ; location of b
mov [ebp - 12], 2   ; location of c
```

How to pass arguments?

- Possible options:
  - In registers
  - On the stack

How to pass arguments?

- x86 32 bit
  - Pass arguments on the stack
  - Return value is in EAX and EDX
- x86 64 bit – more registers!
  - Pass first 6 arguments in registers
    - RDI, RSI, RDX, RCX, R8, and R9
  - The rest on the stack
  - Return value is in RAX and RDX

x86_32: passing arguments on the stack

- Example function

```
void my_function(int x, int y, int z)
{  …  }
```

- Example invocation

```
my_function(2, 5, 10);
```

- Generated code

```
push 10
push 5
push 2
call _my_function
```

Example stack

```
:     :
| 10 |  [ebp + 16] (3rd function argument)
|  5 |  [ebp + 12] (2nd argument)
|  2 |  [ebp + 8]  (1st argument)
| RA |  [ebp + 4]  (return address)
| FP |  [ebp]      (old ebp value) ← EBP points here
|    |  [ebp - 4]  (1st local variable)
:     :
:     :
|    |  [ebp - X]  (esp - the current stack pointer)
```

Example stack

```
:      :
| 10 | [ebp + 16] (3rd function argument)
|  5 | [ebp + 12] (2nd argument)
|  2 | [ebp + 8]  (1st argument)
| RA | [ebp + 4]  (return address)
| FP | [ebp]      (old ebp value) ← EBP points here
|    | [ebp - 4]  (1st local variable)
:      :
:      :
|    | [ebp - X]  (esp - the current stack pointer)
```

Example stack

```
:    :
| 10 | [ebp + 16] (3rd function argument)
|  5 | [ebp + 12] (2nd argument)
|  2 | [ebp + 8]  (1st argument)
| RA | [ebp + 4]  (return address)
| FP | [ebp]      (old ebp value) ← EBP points here
|    | [ebp - 4]  (1st local variable)
:    :
:    :
|    | [ebp - X]  (esp - the current stack pointer)
```

Example stack

```
:    :
| 10 | [ebp + 16] (3rd function argument)
|  5 | [ebp + 12] (2nd argument)
|  2 | [ebp + 8]  (1st argument)
| RA | [ebp + 4]  (return address)
| FP | [ebp]      (old ebp value) ← EBP points here
|    | [ebp - 4]  (1st local variable)
:    :
:    :
|    | [ebp - X]  (esp - the current stack pointer)
```

Example: caller side code

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```
caller:
    ; manage own stack frame
    push    ebp
    mov     ebp, esp
    ; push call arguments
    push    3
    push    2
    push    1
    ; call subroutine 'callee'
    call    callee
    ; remove arguments from frame
    add     esp, 12
    ; use subroutine result
    add     eax, 5
    ; restore old call frame
    pop     ebp
    ; return
    ret
```

Example: caller side code

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```asm
caller:
    ; manage own stack frame
    push    ebp
    mov     ebp, esp
    ; push call arguments
    push    3
    push    2
    push    1
    ; call subroutine 'callee'
    call    callee
    ; remove arguments from frame
    add     esp, 12
    ; use subroutine result
    add     eax, 5
    ; restore old call frame
    pop     ebp
    ; return
    ret
```

Example: caller side code

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```nasm
caller:
  ; manage own stack frame
  push    ebp
  mov     ebp, esp
  ; push call arguments
  push    3
  push    2
  push    1
  ; call subroutine 'callee'
  call    callee
  ; remove arguments from frame
  add     esp, 12
  ; use subroutine result
  add     eax, 5
  ; restore old call frame
  pop     ebp
  ; return
  ret
```

Example: caller side code

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```asm
caller:
  ; manage own stack frame
  push    ebp
  mov     ebp, esp
  ; push call arguments
  push    3
  push    2
  push    1
  ; call subroutine 'callee'
  call    callee
  ; remove arguments from frame
  add     esp, 12
  ; use subroutine result
  add     eax, 5
  ; restore old call frame
  pop     ebp
  ; return
  ret
```

Example: caller side code

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```asm
caller:
  ; manage own stack frame
  push    ebp
  mov     ebp, esp
  ; push call arguments
  push    3
  push    2
  push    1
  ; call subroutine 'callee'
  call    callee
  ; remove arguments from frame
  add     esp, 12
  ; use subroutine result
  add     eax, 5
  ; restore old call frame
  pop     ebp
  ; return
  ret
```

Example: caller side code

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```nasm
caller:
  ; manage own stack frame
  push    ebp
  mov     ebp, esp
  ; push call arguments
  push    3
  push    2
  push    1
  ; call subroutine 'callee'
  call    callee
  ; remove arguments from frame
  add     esp, 12
  ; use subroutine result
  add     eax, 5
  ; restore old call frame
  pop     ebp
  ; return
  ret
```

Wait, where is "return ret;" ?

```c
int callee(int, int, int);

int caller(void)
{
    int ret;

    ret = callee(1, 2, 3);
    ret += 5;
    return ret;
}
```

```
caller:
  ; manage own stack frame
  push    ebp
  mov     ebp, esp
  ; push call arguments
  push    3
  push    2
  push    1
  ; call subroutine 'callee'
  call    callee
  ; remove arguments from frame
  add     esp, 12
  ; use subroutine result
  add     eax, 5
  ; restore old call frame
  pop     ebp
  ; return
  ret
```

Example: callee side code

```c
void my_function(int x, int y, int z)
{
    int a, b, c;
    …
    return;
}
```

```asm
_my_function:
  push ebp
  mov ebp, esp
  sub esp, 12 ; allocate local varaibles
              ; sizeof(a) + sizeof(b) + sizeof(c)
  ; x = [ebp + 8], y = [ebp + 12], z = [ebp + 16]
  ; a=[ebp-4]=[esp+8],
  ; b=[ebp-8]=[esp+4], c=[ebp-12] = [esp]
  mov esp, ebp ; deallocate local variables
  pop ebp
  ret
```

Example: callee side code

```c
void my_function(int x, int y, int z)
{
    int a, b, c;
    …
    return;
}
```

```
_my_function:
  push ebp
  mov ebp, esp
  sub esp, 12 ; allocate local varaibles
              ; sizeof(a) + sizeof(b) + sizeof(c)
  ; x = [ebp + 8], y = [ebp + 12], z = [ebp + 16]
  ; a=[ebp-4]=[esp+8],
  ; b=[ebp-8]=[esp+4], c=[ebp-12] = [esp]
  mov esp, ebp ; deallocate local variables
  pop ebp
  ret
```

Example: callee side code

```c
void my_function(int x, int y, int z)
{
    int a, b, c;
    …
    return;
}
```

```
_my_function:
  push ebp
  mov ebp, esp ; ebp = esp
  sub esp, 12 ; allocate local varaibles
              ; sizeof(a) + sizeof(b) + sizeof(c)
  ; x = [ebp + 8], y = [ebp + 12], z = [ebp + 16]
  ; a=[ebp-4]=[esp+8],
  ; b=[ebp-8]=[esp+4], c=[ebp-12] = [esp]
  mov esp, ebp ;deallocate local variables (esp = ebp)
  pop ebp
  ret
```

Example: callee side code

```
void my_function(int x, int y, int z)
{
    int a, b, c;
    …
    return;
}
```

```
_my_function:
  push ebp
  mov ebp, esp ; ebp = esp
  sub esp, 12 ; allocate local varaibles
              ; sizeof(a) + sizeof(b) + sizeof(c)
  ; x = [ebp + 8], y = [ebp + 12], z = [ebp + 16]
  ; a=[ebp-4]=[esp+8],
  ; b=[ebp-8]=[esp+4], c=[ebp-12] = [esp]
  mov esp, ebp ;deallocate local variables (esp = ebp)
  pop ebp
  ret
```

Example: callee side code

```c
void my_function(int x, int y, int z)
{
    int a, b, c;
    …
    return;
}
```

```
_my_function:
  push ebp
  mov ebp, esp ; ebp = esp
  sub esp, 12 ; allocate local varaibles
              ; sizeof(a) + sizeof(b) + sizeof(c)
  ; x = [ebp + 8], y = [ebp + 12], z = [ebp + 16]
  ; a=[ebp-4]=[esp+8],
  ; b=[ebp-8]=[esp+4], c=[ebp-12] = [esp]
  mov esp, ebp ;deallocate local variables (esp = ebp)
  pop ebp
  ret
```

`leave` instruction

```
void my_function(int x, int y, int z)
{
    int a, b, c;
    …
    return;
}
```

```
_my_function:
  push ebp
  mov ebp, esp ; ebp = esp
  sub esp, 12 ; allocate local varaibles
              ; sizeof(a) + sizeof(b) + sizeof(c)
  ; x = [ebp + 8], y = [ebp + 12], z = [ebp + 16]
  ; a=[ebp-4]=[esp+8],
  ; b=[ebp-8]=[esp+4], c=[ebp-12] = [esp]
  mov esp, ebp
  pop ebp
  ret
```

- x86 has a special instruction for this
  - `leave`

Back to stack frames, so why do we need them?

- … They are not strictly required
- GCC compiler option `-fomit-frame-pointer` can disable them

`Don't keep the frame pointer in a register for functions that don't need one. This avoids the instructions to save, set up and restore frame pointers; it also makes an extra register available in many functions.` **`It also makes debugging impossible on some machines.`**

Referencing args without frames



Initially parameter is

- [ESP + 4]

Later as the function pushes things on the stack it changes, e.g.

- [ESP + 8]

- Debugging becomes hard
  - As ESP changes one has to manually keep track where local variables are relative to ESP (ESP + 4 or +8)
    - **Compiler can easily do this and generate correct code!**
    - **But it's hard for a human**
  - It's hard to unwind the stack in case of a crash
    - To print out a backtrace

And you only save...

- A couple instructions required to maintain the stack frame
- 1 register (EBP)
  - x32 has 8 registers (and one is ESP, so 7 are left)
    - So taking another one is 1/7 or 14.28% of register space
    - Sometimes its worse it!
  - x64 has 16 registers, so it doesn't really matter
- That said, GCC sets `-fomit-frame-pointer` to “on”
  - At -O, -O1, -O2 …
  - Don't get surprised

Relevant part of the GCC manual

3.10 Options That Control Optimization

https://gcc.gnu.org/onlinedocs/gcc/Optimize-Options.html

-O

-O1

With -O, the compiler tries to reduce code size and execution time, without performing any optimizations that take a great deal of compilation time.

-O turns on the following optimization flags:

-fauto-inc-dec

-fbranch-count-reg

...

-fomit-frame-pointer

-freorder-blocks

Saving and restoring registers

Saving register state across invocations

- Processor doesn't save registers
  - General purpose, segment, flags
- Again, a calling convention is needed
  - Agreement on what gets saved by the callee and the caller

Saving register state across invocations

- Registers EAX, ECX, and EDX are caller-saved
  - The function is free to use them
- ... the rest are callee-saved
  - If the function uses them it has to restore them to the original values

- In general there multiple calling conventions
  - We described **cdecl**
  - **Make sure you know what you're doing**
  - https://en.wikipedia.org/wiki/X86_calling_conventions#cdecl

  - It's easy as long as you know how to read the table

Questions?

References

- https://en.wikibooks.org/wiki/X86_Disassembly/Functions_and_Stack_Frames
- https://en.wikipedia.org/wiki/Calling_convention
- https://en.wikipedia.org/wiki/X86_calling_conventions
- http://stackoverflow.com/questions/14666665/trying-to-understand-gcc-option-fomit-frame-pointer